

```
0x4e470x010x00GS108Tv2          5.4.2.33          0x000000000x0000000000000000
```

```
! The line above is the NSDP Text Configuration header. DO NOT EDIT THIS HEADER
```

```
!Current Configuration:
```

```
!
```

```
!System Description "GS108Tv2"
```

```
!System Software Version "5.4.2.33"
```

```
!System Up Time          "0 days 7 hrs 13 mins 27 secs"
```

```
!Additional Packages     FASTPATH QOS
```

```
!Current SNTP Synchronized Time: Mar 25 20:33:41 202 UTC
```

```
!
```

```
network protocol none
```

```
network parms 192.168.123.3 255.255.255.0 192.168.123.1
```

```
vlan database
```

```
set igmp 1
```

```
set igmp groupmembership-interval 1 30
```

```
set igmp querier 1
```

```
set igmp querier 1 address 10.10.10.1
```

```
set igmp querier election participate 1
```

```
set igmp groupmembership-interval 3 30
```

```
set igmp querier 3 address 10.10.10.3
```

```
set igmp querier election participate 3
```

```
exit
```

```
configure
```

```
!
```

```
sntp client mode unicast
```

```
! sntp server status is active
```

```
sntp server 192.168.123.1
```

```
ip name server 192.168.123.1
```

```
users passwd "admin" encrypted
```

```
0a51d780be1a0240b8cc7c69fe0479dbf07644e1094b25fb43ebe2fa72f649e4
```

```
authentication login "defaultList" local
```

```
lineconfig
```

```
exit
```

```
spanning-tree configuration name "10-DA-43-20-3B-6A"
```

```
voip status
```

```
voip oui 00:01:E3 desc SIEMENS
```

```
voip oui 00:03:6B desc CISCO1
voip oui 00:12:43 desc CISCO2
voip oui 00:0F:E2 desc H3C
voip oui 00:60:B9 desc NITSUKO
voip oui 00:D0:1E desc PINTEL
voip oui 00:E0:75 desc VERILINK
voip oui 00:E0:BB desc 3COM
voip oui 00:04:0D desc AVAYA1
voip oui 00:1B:4F desc AVAYA2

auto-video

set igmp querier address 1.1.1.31

interface 0/1

set igmp

set igmp groupmembership-interval 60

vlan participation exclude 3

exit

interface 0/2

set igmp

set igmp groupmembership-interval 60

vlan participation include 3

exit

interface 0/3

set igmp

set igmp groupmembership-interval 60

vlan participation include 3

exit

interface 0/4

set igmp

set igmp groupmembership-interval 60

vlan participation include 3

exit

interface 0/5

set igmp

set igmp groupmembership-interval 60

vlan participation include 3

exit
```

```
interface 0/6
set igmp
set igmp groupmembership-interval 60
vlan participation include 3
exit
interface 0/7
set igmp
set igmp groupmembership-interval 60
vlan participation include 3
exit
interface 0/8
set igmp
set igmp groupmembership-interval 60
vlan participation include 3
exit
interface 3/1
no snmp trap link-status
lacp collector max-delay 0
exit
interface 3/2
no snmp trap link-status
lacp collector max-delay 0
exit
interface 3/3
no snmp trap link-status
lacp collector max-delay 0
exit
interface 3/4
no snmp trap link-status
lacp collector max-delay 0
exit
exit
```